

Clear your web browser's cache, cookies, and history

Mobile browsers

1. Android

The steps to clear your cache, cookies, and history may differ depending on the model of your Android device and your preferred browser, but you should be able to clear your cache and data from your application management settings menu:

1. Go to **Settings** and choose **Apps** or **Application Manager**.
2. Swipe to the **All** tab.
3. In the list of installed apps, find and tap your web browser. Tap **Clear Data** and then **Clear Cache**.
4. Exit/quit all browser windows and re-open the browser.

2. Chrome for Android

1. Tap **Chrome menu > Settings**.
2. Tap **(Advanced) Privacy**.
3. From the "Time Range" drop-down menu, select **All Time**.
4. Check **Cookies and Site data** and **Cached Images and Files**.
5. Tap **Clear data**.
6. Exit/quit all browser windows and re-open the browser.

3. Safari for iOS

1. Open your **Settings** app.
2. Tap **Safari**.
3. Tap **Clear History and Website Data** and confirm.
4. Exit/quit all browser windows and re-open the browser.

4. Chrome for iOS

1. Tap **Chrome menu > Settings**.
2. Tap **Privacy**.
3. Tap **Clear Browsing Data**.

4. Choose the data type you want to clear.
5. Tap Clear Browsing Data.
6. Exit/quit all browser windows and re-open the browser.

2. Desktop browsers

1. Chrome

1. In the browser bar, enter:

```
chrome://settings/clearBrowserData
```

2. At the top of the "Clear browsing data" window, click Advanced.
3. Select the following:
 - Browsing history
 - Download history
 - Cookies and other site data
 - Cached images and files

From the "Time range" drop-down menu, you can choose the period of time for which you want to clear cached information. To clear your entire cache, select All time.

4. Click CLEAR DATA.
5. Exit/quit all browser windows and re-open the browser.

2. Firefox

1. From the History menu, select Clear Recent History.

If the menu bar is hidden, press **Alt** to make it visible.

2. From the Time range to clear: drop-down menu, select the desired range; to clear your entire cache, select Everything.
3. Next to "Details", click the down arrow to choose which elements of the history to clear; to clear your entire cache, select all items.
4. Click Clear Now.
5. Exit/quit all browser windows and re-open the browser.

3. Microsoft Edge

1. In the top right, click the Hub icon (looks like star with three horizontal lines).
2. Click the History icon (looks like a clock), and then select **Clear all history**.
3. Select **Browsing history**, then **Cookies and saved website data**, and then **Cached data and files**. Click **Clear**.
4. After the "All Clear!" message appears, exit/quit all browser windows and re-open the browser.

4. Internet Explorer 11

Select **Tools > Safety > Delete browsing history...**

If the menu bar is hidden, press **Alt** to make it visible.

1. Deselect **Preserve Favorites website data**, and select:
 - **Temporary Internet files** or **Temporary Internet files and website files**
 - **Cookies** or **Cookies and website data**
 - **History**
2. Click **Delete**. You will see a confirmation at the bottom of the window when the process is complete.
3. Exit/quit all browser windows and re-open the browser.

5. Opera

1. From the **Opera** menu, select **Settings**, then **Privacy & Security**, and then **Clear browsing data...**
2. In the dialog box that opens, from the "Obliterate the following items from:" drop-down menu, select **The beginning of time**.
3. Select the following:
 - **Browsing history**
 - **Download history**
 - **Cookies and other site data**
 - **Cached images and files**
4. Click **Clear browsing data**.

5. Exit/quit all browser windows and re-open the browser.

6.Safari 8 and later

1. From the Safari menu, select Clear History... or Clear History and Website Data...
2. Select the desired time range, and then click Clear History.
3. Go to Safari > Quit Safari or press **Command-Q** to exit the browser completely.